



FrameLink Express Upgrade Instructions

You must first:

Download the new application installer file from the web site.

(File is called “FL_Express_Software_a_b_c_d.exe” where a.b.c.d represents the version number)

Download the new firmware installer file from the web site.

(File is called “FL_Express_Firmware_a_b_c_d.exe” where a.b.c.d represents the version number).

Then use the following steps to install newly released FrameLink Express software and firmware.

1. Remove the old application files
2. Install the new application files
3. Replace the old driver with the new driver
4. Upgrade the card with the new firmware

(Note: in the following instructions ‘click’ refers to the left mouse button)

1. To remove the old application files:


- 1.1 Click on “*Start*”.
- 1.2 Click on “*Settings*”.
- 1.3 Click on “*Control Panel*”.
- 1.4 For Windows XP 32 or 64 bit: Double click on “*Add or Remove Programs*”.
For Windows Vista 32 or 64 bit: Double click on “*Programs and Features*”.
- 1.5 Click on “*FrameLink Express*”.
- 1.6 Click on “*Remove*”.
- 1.7 Follow the on screen instructions.
- 1.8 When the message ‘Uninstall Complete’ appears, click “*Finish*”.

2. To install the new application files:

- 2.1 Double click on the ‘FL_Express_Software_a_b_c_d.exe’ file.
- 2.2 Wait for the ‘FrameLink Express - InstallShield Wizard’ screen to appear.
- 2.3 Follow the on-screen instructions.
- 2.4 For Windows XP 32 bit and Windows XP 64 bit, click “*Continue Anyway*” to continue.



- 2.5 For Windows Vista 32 bit and Windows Vista 64 bit, select “*Always trust software from Imperx, Inc.*” and click on “*Install*” button, when the following message appears:



- 2.6 When the following message appears, choose if you would like to register online by clicking on “*Register now*” or “*Skip*”.



- 2.7 When prompted, select “*Reboot now*” and click “*Finish*”.
- 2.8 This completes the software installation.

3. **To replace the old driver with the new driver:**

3.1 Insert the FrameLink Express card into the laptop.

3.2 For Windows XP 32 bit and for Windows XP 64 bit:

Wait for the system to prompt you with a “Found New Hardware Wizard” dialog box. Proceed to Step 3.3.

For Windows Vista:

The driver will automatically be installed.


Proceed to step 3.11.

3.3 Under certain conditions, the following message may appear:




If this message appears, click “*No, not this time*”, then click “*Next*”.

3.4 When the following message appears, select “*Install from a list or specified location (Advanced)*”, then click “*Next*”.




3.5 When the following message appears, select “*Don’t search. I will choose the driver to install*”, then click “*Next*”.




3.6 Click on “*Have Disk...*” and browse to the folder: C:\Program Files\ImperX\Framelink Express\Drivers\Kernel” then click “Open”.


3.7 When the following message appears, click “OK”.



3.8 When the following message appears, click “Next”.



3.9 The following message will appear:



3.10 Click “*Continue Anyway*” to continue.

3.11 When “Click finish to close the wizard” appears, click on “*Finish*”.

3.12 This completes the driver installation.

4 To upgrade the card with the new firmware:

4.1 Insert the FrameLink Express card into the laptop.

4.2 Double click on the ‘FL_Express_Firmware_a_b_c_d.exe’ file.

4.3 Click on “*Start*”.

4.4 When the message ‘Resetting....done’ appears, click on “*Exit*”.

Important notes:

Do not interrupt the firmware upgrade process!

Do not remove the card during firmware upgrade!

Do not reboot the PC during firmware upgrade!

If the firmware upgrade fails, then click on “*Exit*” and repeat from step 4.2

4.5 This completes the firmware upgrade.

4.6 Reboot the PC.